

ESD Essentials Term Paper Evaluation

Generated by Doxygen 1.14.0

1 Namespace Index	1
1.1 Package List	1
2 Class Index	3
2.1 Class List	3
3 File Index	5
3.1 File List	5
4 Namespace Documentation	7
4.1 test1 Namespace Reference	7
4.1.1 Function Documentation	8
4.1.1.1 read_csv_data()	8
4.1.1.2 read_ultrasonic()	8
4.1.2 Variable Documentation	8
4.1.2.1 app	8
4.1.2.2 DHT_PIN	9
4.1.2.3 DHT_SENSOR	9
4.1.2.4 file_lock	9
4.1.2.5 filename	9
4.1.2.6 GAS_DO_PIN	9
4.1.2.7 mode	9
4.1.2.8 newline	10
4.1.2.9 root	10
4.1.2.10 ULTRASONIC_ECHO	10
4.1.2.11 ULTRASONIC_TRIG	10
4.1.2.12 writer	10
5 Class Documentation	11
5.1 test1.SensorApp Class Reference	11
5.1.1 Detailed Description	12
5.1.2 Constructor & Destructor Documentation	12
5.1.2.1 __init__()	12
5.1.3 Member Function Documentation	12
5.1.3.1 on_close()	12
5.1.3.2 sensor_loop()	13
5.1.3.3 start_sensor_thread()	13
5.1.3.4 update_gas_label()	13
5.1.3.5 update_plots()	13
5.1.3.6 update_temp_label()	14
5.1.4 Member Data Documentation	14
5.1.4.1 axs	14
5.1.4.2 canvas	14
5.1.4.3 fig	14

5.1.4.4 gas_slider	14
5.1.4.5 gas_threshold	14
5.1.4.6 gas_value_label	14
5.1.4.7 gas_values	15
5.1.4.8 levels	15
5.1.4.9 on_close	15
5.1.4.10 root	15
5.1.4.11 sensor_thread	15
5.1.4.12 status_label	15
5.1.4.13 temp_slider	15
5.1.4.14 temp_threshold	16
5.1.4.15 temp_value_label	16
5.1.4.16 temps	16
5.1.4.17 times	16
5.1.4.18 update_plots	16
6 File Documentation	17
6.1 test1.py File Reference	17
6.2 test1.py	18

Chapter 1

Namespace Index

1.1 Package List

Here are the packages with brief descriptions (if available):

test1	7
---------------------------------	-------------------

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

test1.SensorApp	A GUI application for real-time visualization and monitoring of sensor data	11
---------------------------------	---	----

Chapter 3

File Index

3.1 File List

Here is a list of all files with brief descriptions:

test1.py	17
--------------------------	-------	----

Chapter 4

Namespace Documentation

4.1 test1 Namespace Reference

Classes

- class [SensorApp](#)
A GUI application for real-time visualization and monitoring of sensor data.

Functions

- [read_ultrasonic](#) ()
Reads distance (in cm) from the HC-SR04 ultrasonic sensor.
- [read_csv_data](#) ()
Reads data from the CSV log file.

Variables

- int [DHT_PIN](#) = 17
DHT11 data pin.
- int [GAS_DO_PIN](#) = 27
MQ Gas Sensor digital output pin.
- int [ULTRASONIC_TRIG](#) = 23
Ultrasonic sensor TRIG pin.
- int [ULTRASONIC_ECHO](#) = 24
Ultrasonic sensor ECHO pin.
- [DHT_SENSOR](#) = Adafruit_DHT.DHT11
Sensor type for DHT.
- str [filename](#) = "essentials_log.csv"
CSV filename for data logging.
- [file_lock](#) = threading.Lock()
Thread lock to synchronize file access.
- [mode](#)
- [newline](#)
- [writer](#) = csv.writer(file)
- [root](#) = tk.Tk()
- [app](#) = [SensorApp](#)(root)

4.1.1 Function Documentation

4.1.1.1 `read_csv_data()`

```
test1.read_csv_data ()
```

Reads data from the CSV log file.

Returns

Four lists containing timestamps, temperature, gas, and level data.

Definition at line 117 of file [test1.py](#).

4.1.1.2 `read_ultrasonic()`

```
test1.read_ultrasonic ()
```

Reads distance (in cm) from the HC-SR04 ultrasonic sensor.

Returns

Distance in centimeters (float), or None if timeout occurs.

Definition at line 88 of file [test1.py](#).

Here is the caller graph for this function:



4.1.2 Variable Documentation

4.1.2.1 `app`

```
test1.app = SensorApp(root)
```

Definition at line 324 of file [test1.py](#).

4.1.2.2 DHT_PIN

```
int test1.DHT_PIN = 17
```

DHT11 data pin.

Definition at line 43 of file [test1.py](#).

4.1.2.3 DHT_SENSOR

```
test1.DHT_SENSOR = Adafruit_DHT.DHT11
```

Sensor type for DHT.

Definition at line 51 of file [test1.py](#).

4.1.2.4 file_lock

```
test1.file_lock = threading.Lock()
```

Thread lock to synchronize file access.

Definition at line 67 of file [test1.py](#).

4.1.2.5 filename

```
test1.filename = "essentials_log.csv"
```

CSV filename for data logging.

Definition at line 64 of file [test1.py](#).

4.1.2.6 GAS_DO_PIN

```
int test1.GAS_DO_PIN = 27
```

MQ Gas Sensor digital output pin.

Definition at line 45 of file [test1.py](#).

4.1.2.7 mode

```
test1.mode
```

Definition at line 72 of file [test1.py](#).

4.1.2.8 newline

```
test1.newline
```

Definition at line 78 of file [test1.py](#).

4.1.2.9 root

```
test1.root = tk.Tk()
```

Definition at line 323 of file [test1.py](#).

4.1.2.10 ULTRASONIC_ECHO

```
int test1.ULTRASONIC_ECHO = 24
```

Ultrasonic sensor ECHO pin.

Definition at line 49 of file [test1.py](#).

4.1.2.11 ULTRASONIC_TRIG

```
int test1.ULTRASONIC_TRIG = 23
```

Ultrasonic sensor TRIG pin.

Definition at line 47 of file [test1.py](#).

4.1.2.12 writer

```
test1.writer = csv.writer(file)
```

Definition at line 79 of file [test1.py](#).

Chapter 5

Class Documentation

5.1 test1.SensorApp Class Reference

A GUI application for real-time visualization and monitoring of sensor data.

Public Member Functions

- `__init__` (self, root)
Constructor for initializing the GUI layout and logic.
- `update_temp_label` (self, event=None)
Updates temperature slider label.
- `update_gas_label` (self, event=None)
Updates gas slider label.
- `start_sensor_thread` (self)
Starts a background thread for continuous sensor data acquisition.
- `sensor_loop` (self)
Sensor data acquisition loop (runs on a background thread).
- `update_plots` (self)
Updates live Matplotlib plots on the GUI.
- `on_close` (self)
Handles cleanup when closing the GUI.

Public Attributes

- `root` = root
- `temp_threshold` = tk.DoubleVar(value=50)
- `gas_threshold` = tk.IntVar(value=1)
- list `times` = []
- list `temps` = []
- list `gas_values` = []
- list `levels` = []
- `fig`
- `axs` = plt.subplots(3, 1, figsize=(8, 6), sharex=True)
- `canvas` = FigureCanvasTkAgg(self.fig, master=root)

- `temp_slider` = `ttk.Scale(root, from_=0, to=100, orient='horizontal', variable=self.temp_threshold, command=self.update_temp_label)`
- `temp_value_label` = `ttk.Label(root, text=f"{self.temp_threshold.get():.1f}")`
- `gas_slider` = `ttk.Scale(root, from_=0, to=1, orient='horizontal', variable=self.gas_threshold, command=self.update_gas_label)`
- `gas_value_label` = `ttk.Label(root, text=f"{int(self.gas_threshold.get())}")`
- `status_label` = `ttk.Label(root, text="", font=("Arial", 14))`
- `on_close`
- `sensor_thread` = `threading.Thread(target=self.sensor_loop, daemon=True)`
- `update_plots`

5.1.1 Detailed Description

A GUI application for real-time visualization and monitoring of sensor data.

This class creates a Tkinter window embedding live-updating Matplotlib plots for temperature, gas concentration, and water level readings.

It also continuously logs sensor data into a CSV file using a background thread.

Responsibilities:

- Acquire and log sensor data.
- Dynamically plot readings in real-time.
- Provide fault/anomaly detection.
- Allow runtime adjustment of sensor thresholds.

Definition at line 153 of file `test1.py`.

5.1.2 Constructor & Destructor Documentation

5.1.2.1 `__init__()`

```
test1.SensorApp.__init__ (
    self,
    root)
```

Constructor for initializing the GUI layout and logic.

Parameters

<code>root</code>	The main Tkinter window.
--	

Definition at line 156 of file `test1.py`.

5.1.3 Member Function Documentation

5.1.3.1 on_close()

```
test1.SensorApp.on_close (  
    self)
```

Handles cleanup when closing the GUI.

Definition at line 312 of file [test1.py](#).

5.1.3.2 sensor_loop()

```
test1.SensorApp.sensor_loop (  
    self)
```

Sensor data acquisition loop (runs on a background thread).

Reads DHT11, MQ gas sensor, and ultrasonic distance data periodically. Logs results to CSV and updates internal memory.

Definition at line 216 of file [test1.py](#).

Here is the call graph for this function:



5.1.3.3 start_sensor_thread()

```
test1.SensorApp.start_sensor_thread(  
    self)
```

Starts a background thread for continuous sensor data acquisition.

Definition at line 208 of file [test1.py](#).

5.1.3.4 update_gas_label()

```
test1.SensorApp.update_gas_label (  
    self,  
    event = None)
```

Updates gas slider label.

Definition at line 204 of file [test1.py](#).

5.1.3.5 update_plots()

```
test1.SensorApp.update_plots (
    self)
```

Updates live Matplotlib plots on the GUI.

Definition at line 262 of file [test1.py](#).

5.1.3.6 update_temp_label()

```
test1.SensorApp.update_temp_label (
    self,
    event = None)
```

Updates temperature slider label.

Definition at line 200 of file [test1.py](#).

5.1.4 Member Data Documentation

5.1.4.1 `axs`

```
test1.SensorApp.axs = plt.subplots(3, 1, figsize=(8, 6), sharex=True)
```

Definition at line 171 of file [test1.py](#).

5.1.4.2 `canvas`

```
test1.SensorApp.canvas = FigureCanvasTkAgg(self.fig, master=root)
```

Definition at line 174 of file [test1.py](#).

5.1.4.3 `fig`

```
test1.SensorApp.fig
```

Definition at line 171 of file [test1.py](#).

5.1.4.4 `gas_slider`

```
test1.SensorApp.gas_slider = ttk.Scale(root, from_=0, to=1, orient='horizontal', variable=self.gas_threshold, command=self.update_gas_label)
```

Definition at line 185 of file [test1.py](#).

5.1.4.5 gas_threshold

```
test1.SensorApp.gas_threshold = tk.IntVar(value=1)
```

Definition at line 162 of file [test1.py](#).

5.1.4.6 gas_value_label

```
test1.SensorApp.gas_value_label = ttk.Label(root, text=f"{int(self.gas_threshold.get())}")
```

Definition at line 187 of file [test1.py](#).

5.1.4.7 gas_values

```
test1.SensorApp.gas_values = []
```

Definition at line 167 of file [test1.py](#).

5.1.4.8 levels

```
test1.SensorApp.levels = []
```

Definition at line 168 of file [test1.py](#).

5.1.4.9 on_close

```
test1.SensorApp.on_close
```

Definition at line 197 of file [test1.py](#).

5.1.4.10 root

```
test1.SensorApp.root = root
```

Definition at line 157 of file [test1.py](#).

5.1.4.11 sensor_thread

```
test1.SensorApp.sensor_thread = threading.Thread(target=self.sensor_loop, daemon=True)
```

Definition at line 209 of file [test1.py](#).

5.1.4.12 status_label

```
test1.SensorApp.status_label = ttk.Label(root, text="", font=("Arial", 14))
```

Definition at line 190 of file [test1.py](#).

5.1.4.13 temp_slider

```
test1.SensorApp.temp_slider = ttk.Scale(root, from_=0, to=100, orient='horizontal', variable=self.temp_threshold, command=self.update_temp_label)
```

Definition at line 179 of file [test1.py](#).

5.1.4.14 temp_threshold

```
test1.SensorApp.temp_threshold = tk.DoubleVar(value=50)
```

Definition at line 161 of file [test1.py](#).

5.1.4.15 temp_value_label

```
test1.SensorApp.temp_value_label = ttk.Label(root, text=f"{self.temp_threshold.get():.1f}")
```

Definition at line 181 of file [test1.py](#).

5.1.4.16 temps

```
test1.SensorApp.temps = []
```

Definition at line 166 of file [test1.py](#).

5.1.4.17 times

```
test1.SensorApp.times = []
```

Definition at line 165 of file [test1.py](#).

5.1.4.18 update_plots

```
test1.SensorApp.update_plots
```

Definition at line 309 of file [test1.py](#).

The documentation for this class was generated from the following file:

- [test1.py](#)

Chapter 6

File Documentation

6.1 test1.py File Reference

Classes

- class `test1.SensorApp`
A GUI application for real-time visualization and monitoring of sensor data.

Namespaces

- namespace `test1`

Functions

- `test1.read_ultrasonic ()`
Reads distance (in cm) from the HC-SR04 ultrasonic sensor.
- `test1.read_csv_data ()`
Reads data from the CSV log file.

Variables

- int `test1.DHT_PIN` = 17
DHT11 data pin.
- int `test1.GAS_DO_PIN` = 27
MQ Gas Sensor digital output pin.
- int `test1.ULTRASONIC_TRIG` = 23
Ultrasonic sensor TRIG pin.
- int `test1.ULTRASONIC_ECHO` = 24
Ultrasonic sensor ECHO pin.
- `test1.DHT_SENSOR` = `Adafruit_DHT.DHT11`
Sensor type for DHT.
- str `test1.filename` = "essentials_log.csv"
CSV filename for data logging.
- `test1.file_lock` = `threading.Lock()`
Thread lock to synchronize file access.
- `test1.mode`
- `test1.newline`
- `test1.writer` = `csv.writer(file)`
- `test1.root` = `tk.Tk()`
- `test1.app` = `SensorApp(root)`

6.2 test1.py

[Go to the documentation of this file.](#)

```

00001
00025
00026 import tkinter as tk
00027 from tkinter import ttk
00028 from tkinter import messagebox
00029 import RPi.GPIO as GPIO
00030 import Adafruit_DHT
00031 import time
00032 import csv
00033 from datetime import datetime
00034 from matplotlib.backends.backend_tkagg import FigureCanvasTkAgg
00035 import matplotlib.pyplot as plt
00036 import threading
00037
00038 # =====
00039 #                               GPIO AND SENSOR CONFIGURATION
00040 # =====
00041
00042
00043 DHT_PIN = 17
00044
00045 GAS_DO_PIN = 27
00046
00047 ULTRASONIC_TRIG = 23
00048
00049 ULTRASONIC_ECHO = 24
00050
00051 DHT_SENSOR = Adafruit_DHT.DHT11
00052
00053 # GPIO mode and pin setup
00054 GPIO.setmode(GPIO.BCM)
00055 GPIO.setup(GAS_DO_PIN, GPIO.IN)
00056 GPIO.setup(ULTRASONIC_TRIG, GPIO.OUT)
00057 GPIO.setup(ULTRASONIC_ECHO, GPIO.IN)
00058
00059 # =====
00060 #                               CSV FILE INITIALIZATION
00061 # =====
00062
00063
00064 filename = "essentials_log.csv"
00065
00066
00067 file_lock = threading.Lock()
00068
00069 # @brief Initialize CSV file with header if empty
00070 with file_lock:
00071     try:
00072         with open(filename, mode='r') as f:
00073             if f.read(1):
00074                 pass
00075             else:
00076                 raise FileNotFoundError
00077     except (FileNotFoundError, IOError):
00078         with open(filename, mode='w', newline='') as file:
00079             writer = csv.writer(file)
00080             writer.writerow(["Timestamp", "TEMP", "PPM", "LEVEL", "Anomaly"])
00081
00082 # =====
00083 #                               SENSOR READING FUNCTIONS
00084 # =====
00085
00086
00087 def read_ultrasonic():
00088     GPIO.output(ULTRASONIC_TRIG, False)
00089     time.sleep(0.1)
00090
00091     GPIO.output(ULTRASONIC_TRIG, True)
00092     time.sleep(0.00001)
00093     GPIO.output(ULTRASONIC_TRIG, False)
00094
00095     pulse_start = time.time()
00096     timeout = pulse_start + 0.04
00097     while GPIO.input(ULTRASONIC_ECHO) == 0:
00098         pulse_start = time.time()
00099         if pulse_start > timeout:
00100             return None
00101
00102     pulse_end = time.time()
00103     timeout = pulse_end + 0.04
00104     while GPIO.input(ULTRASONIC_ECHO) == 1:
00105         pulse_end = time.time()

```

```

00107         if pulse_end > timeout:
00108             return None
00109
00110         pulse_duration = pulse_end - pulse_start
00111         distance_cm = pulse_duration * 17150
00112         return round(distance_cm, 2)
00113
00114
00115
00117 def read_csv_data():
00118     times, temps, gas_values, levels = [], [], [], []
00119     with file_lock:
00120         try:
00121             with open(filename, mode='r') as file:
00122                 reader = csv.DictReader(file)
00123                 for row in reader:
00124                     try:
00125                         times.append(datetime.strptime(row["Timestamp"], "%Y-%m-%d %H:%M:%S"))
00126                         temps.append(float(row["TEMP"]) if row["TEMP"] != "N/A" else None)
00127                         gas_values.append(int(row["PPM"]))
00128                         levels.append(float(row["LEVEL"]) if row["LEVEL"] != "N/A" else None)
00129                     except Exception:
00130                         continue
00131         except FileNotFoundError:
00132             pass
00133     return times, temps, gas_values, levels
00134
00135
00136 # =====
00137 #                               MAIN APPLICATION CLASS
00138 # =====
00139
00140
00152
00153 class SensorApp:
00154
00156     def __init__(self, root):
00157         self.root = root
00158         self.root.title("Sensor Monitoring and Visualization")
00159
00160         # Threshold variables
00161         self.temp_threshold = tk.DoubleVar(value=50)
00162         self.gas_threshold = tk.IntVar(value=1)
00163
00164         # Data containers for live updates
00165         self.times = []
00166         self.temps = []
00167         self.gas_values = []
00168         self.levels = []
00169
00170         # ----- GUI Configuration -----
00171         self.fig, self.axs = plt.subplots(3, 1, figsize=(8, 6), sharex=True)
00172         self.fig.tight_layout(pad=3)
00173
00174         self.canvas = FigureCanvasTkAgg(self.fig, master=root)
00175         self.canvas.get_tk_widget().grid(row=0, column=0, columnspan=6, padx=10, pady=10)
00176
00177         # Sliders and labels for thresholds
00178         ttk.Label(root, text="Temperature Threshold (°C)").grid(row=1, column=0, sticky="w", padx=10)
00179         self.temp_slider = ttk.Scale(root, from_=0, to=100, orient='horizontal',
variable=self.temp_threshold, command=self.update_temp_label)
00180         self.temp_slider.grid(row=1, column=1, sticky="ew", padx=(0,5))
00181         self.temp_value_label = ttk.Label(root, text=f"{self.temp_threshold.get():.1f}")
00182         self.temp_value_label.grid(row=1, column=2, sticky="w")
00183
00184         ttk.Label(root, text="Gas Threshold (PPM, 0 or 1)").grid(row=1, column=3, sticky="w", padx=10)
00185         self.gas_slider = ttk.Scale(root, from_=0, to=1, orient='horizontal',
variable=self.gas_threshold, command=self.update_gas_label)
00186         self.gas_slider.grid(row=1, column=4, sticky="ew", padx=(0,5))
00187         self.gas_value_label = ttk.Label(root, text=f"{int(self.gas_threshold.get())}")
00188         self.gas_value_label.grid(row=1, column=5, sticky="w")
00189
00190         self.status_label = ttk.Label(root, text="", font=("Arial", 14))
00191         self.status_label.grid(row=2, column=0, columnspan=6, pady=10)
00192
00193         # Start live updates
00194         self.update_plots()
00195         self.start_sensor_thread()
00196
00197         root.protocol("WM_DELETE_WINDOW", self.on_close)
00198
00199
00200     def update_temp_label(self, event=None):
00201         self.temp_value_label.config(text=f"{self.temp_threshold.get():.1f}")
00202
00203
00204     def update_gas_label(self, event=None):

```

```

00205         self.gas_value_label.config(text=f"{int(round(self.gas_threshold.get()))}")
00206
00207
00208     def start_sensor_thread(self):
00209         self.sensor_thread = threading.Thread(target=self.sensor_loop, daemon=True)
00210         self.sensor_thread.start()
00211
00212
00216     def sensor_loop(self):
00217         while True:
00218             timestamp = datetime.now().strftime("%Y-%m-%d %H:%M:%S")
00219
00220             humidity, temperature = Adafruit_DHT.read(DHT_SENSOR, DHT_PIN)
00221             temp_val = temperature if temperature is not None else "N/A"
00222
00223             gas_state = GPIO.input(GAS_DO_PIN)
00224             gas_detected = (gas_state == 0)
00225             ppm_val = 1 if gas_detected else 0
00226
00227             level = read_ultrasonic()
00228             level_val = level if level is not None else "N/A"
00229
00230             # Simple anomaly detection logic
00231             anomaly = "No"
00232             if temp_val == "N/A" or level_val == "N/A":
00233                 anomaly = "Yes"
00234             else:
00235                 if not (0 <= temp_val <= 50) or not (0 <= level_val <= 400):
00236                     anomaly = "Yes"
00237
00238             # Thread-safe CSV writing
00239             with file_lock:
00240                 with open(filename, mode='a', newline='') as file:
00241                     writer = csv.writer(file)
00242                     writer.writerow([timestamp, temp_val, ppm_val, level_val, anomaly])
00243
00244             # Data update
00245             dt = datetime.strptime(timestamp, "%Y-%m-%d %H:%M:%S")
00246             self.times.append(dt)
00247             self.temps.append(float(temp_val) if temp_val != "N/A" else None)
00248             self.gas_values.append(ppm_val)
00249             self.levels.append(float(level_val) if level_val != "N/A" else None)
00250
00251             # Maintain buffer size
00252             max_len = 100
00253             if len(self.times) > max_len:
00254                 self.times = self.times[-max_len:]
00255                 self.temps = self.temps[-max_len:]
00256                 self.gas_values = self.gas_values[-max_len:]
00257                 self.levels = self.levels[-max_len:]
00258
00259             time.sleep(0.5)
00260
00261
00262     def update_plots(self):
00263         for ax in self.axes:
00264             ax.clear()
00265
00266             # --- Temperature ---
00267             if self.times and any(t is not None for t in self.temps):
00268                 temps_clean = [t if t is not None else float('nan') for t in self.temps]
00269                 self.axes[0].plot(self.times, temps_clean, 'r-', label='Temperature (°C)')
00270                 self.axes[0].axhline(self.temp_threshold.get(), color='r', linestyle='--', label='Temp
Threshold')
00271                 self.axes[0].set_ylabel("Temperature (°C)")
00272                 self.axes[0].legend(loc='upper right')
00273                 self.axes[0].grid(True)
00274
00275             # --- Gas PPM ---
00276             if self.times:
00277                 self.axes[1].step(self.times, self.gas_values, 'g-', label='Gas PPM')
00278                 self.axes[1].axhline(self.gas_threshold.get(), color='g', linestyle='--', label='Gas
Threshold')
00279                 self.axes[1].set_ylabel("Gas PPM")
00280                 self.axes[1].set_ylim(-0.1, 1.1)
00281                 self.axes[1].legend(loc='upper right')
00282                 self.axes[1].grid(True)
00283
00284             # --- Ultrasonic Level ---
00285             if self.times and any(l is not None for l in self.levels):
00286                 levels_clean = [l if l is not None else float('nan') for l in self.levels]
00287                 self.axes[2].plot(self.times, levels_clean, 'b-', label='Level (cm)')
00288                 self.axes[2].set_ylabel("Level (cm)")
00289                 self.axes[2].set_xlabel("Time")
00290                 self.axes[2].legend(loc='upper right')
00291                 self.axes[2].grid(True)
00292

```



```
00293         self.fig.autofmt_xdate()
00294         self.canvas.draw()
00295
00296         # Fault detection and GUI update
00297         fault_msg = ""
00298         if self.temps and self.gas_values and self.levels:
00299             last_temp = self.temps[-1]
00300             last_gas = self.gas_values[-1]
00301             last_level = self.levels[-1]
00302
00303             if last_temp is None or last_level is None:
00304                 fault_msg = "Critical fault: Sensor data missing!"
00305             elif last_temp > self.temp_threshold.get() or last_gas > self.gas_threshold.get() or not
(0 <= last_level <= 400):
00306                 fault_msg = "Critical fault detected!"
00307
00308         self.status_label.config(text=fault_msg, foreground='red' if fault_msg else 'green')
00309         self.root.after(1000, self.update_plots)
00310
00311
00312     def on_close(self):
00313         GPIO.cleanup()
00314         self.root.destroy()
00315
00316
00317 # =====
00318 #                               MAIN PROGRAM ENTRY POINT
00319 # =====
00320
00321
00322 if __name__ == "__main__":
00323     root = tk.Tk()
00324     app = SensorApp(root)
00325     root.mainloop()
```

